Oasys T/HIS

T/HIS 17.0



- <u>User Interface Improvements</u>
- <u>T/HIS \rightarrow PRIMER link</u>
- <u>Equations</u>
- <u>Add REPORTER to your Workflow</u> (a new, integrated D3PLOT ↔ T/HIS ↔ REPORTER link)
- <u>Curve Locking and Freezing</u>
- <u>User-defined Colours</u>
- <u>Datums</u>
- <u>New Preferences</u>
- <u>New Command Line Options</u>
- FAST-TCF
- <u>JavaScript</u>
- <u>Replay of drag-drop files</u>





User Interface Improvements





Themes

For a more comfortable and accessible experience:

- We have introduced three new theme options:
 - Light
 - Dark
 - Classic
- Buttons have been flattened with their corners rounded to give a more modern look and feel.

						Dana Mumba	a. De		N. NI
						Page Numbe			PI PPI
						Tools		RE REPORTE	R PR PRIMER
			Page Number				Write	Curves	Models
			Tools		RE REPORTE	R PR PRIMER	Style	Properties	Images
Page Number	n (4		H	Write	Curves	Models	Maths	Automotive	Seismic
Taala				Style	Properties	Images	FAST-TCF	Title/Axes	Display
- 100IS	11/-3-	REPORTE	R PR PRIMER	Maths	Automotive	Seismic	Measure	Groups	Graphs
Read	vvrite Otude	Curves	Models	FAST-TCF	Title/Axes	Display	Units	JavaScript	Datum
Concento	Style	Automotivo	Caiamia	Measure	Groups	Graphs	GI		
Uperate	Maths	Title/Axee	Display	Units	JavaScript	Datum			
Rottingo	Hannura	Croups	Oranha	G1 ►			Read	l Data	? >
Command Eil	lložo	LavaSoriat	Datum				Groups	Keyword	T/HIS Curve
		JavaScript	Datum	Dear	l Data	? X	Keyboard	CSV	Screen
None				Real			LS-PREPOST	DIAdem	NASTRAN
Homo				Groups	Keyword	T/HIS Curve	Equation		
<< Undock	Read	d Data	? X	, Keyboard	CSV	Screen	Dert	Dart Crown	Nada
LS-DYNA	Groups	Keyword	T/HIS Curve	LS-PREPOST	DIAdem	NASTRAN	Part V	Choll 1	Thick Shall
Bulk Data	Keyboard	CSV	Screen	Equation			Spring V	Airbag	Contact
ISO	LS-PREPOST	DIAdem	NASTRAN	Part 🔻	Part Group 🔻	Node 🔻	Seatbalt V	Petractor	Slipring
CURVOUT	Equation			Beam ▼	Shell 🔻	Thick Shell V		X Section	Subsystem V
Global 🔻	Part V	Part Group	Node v	Spring V	Airbag ▼	Contact V	Spotweld V	SPC	Boundary V
Solid V	Beam V	Shell V	Thick Shell	Seatbelt V	Retractor	Slipring	SPH V	Tracer	Pulley V
Stonewall V	Spring V	Airban V	Contact V	Joint v	X Section V	Subsystem V	CESE	EM	PBLAST V
Geo Contact	Seathelt V	Retractor	Slipring	Spotweld V	SPC V	Boundary V	Bearing V	CURVOUT	
Reaction V	Joint V	X Section V	Subsystem V	SPH V	Tracer V	Pulley V			
Rigid Body V	Spotweld V	SPC V	Boundary V	CESE	EM	PBLAST V	als New	Model F	eread Model
FSI	SPH V	Tracer V	Pullev V	Bearing ▼	CURVOUT V		irve: <mark>% (highe</mark>	st+1) .	
ICFD		EM	PBLAST V	ls New	Model R	eread Model	r in :		Apply
Pres Tube V	Bearing V	CURVOUT V		rve: % (highe	st+1)		e step	— e	ntities 巜
Calent Made	ala Naur	Madal D	aroad Madal	in :		Apply	etic energy	Sort	By Model 🔻
Select Mode	eis new	Model R	eread model	e sten		ntities {{	nal energy		None
Output cu	urve: % (highe	st+1) .		tic energy	Sort	By Model W	onewall energ	ly Out	
Key	y in :		Apply	hal energy			ring and damp	er e Sek	ct MODEL(S)
DT - Tim	ne step	— Е	ntities 代 🗌	onewall energy		None	urglass energy	y	IDIE MODEI
KE - Kin	etic energy	Sort 8	By Model 🔻	ing and damp	er e Sele	ct MODEL(s)	stem damping	ene	
IE - Inter	mal energy	AI	None	irglass energ	y M1:Wh	ole Model	t internal ener	9У	
SWE - St	tonewall energ	JY Sala	ot MODEL (a)	stem damping	ene		ing interface e	nerg	
SPE - Sp	oring and damp	ere M1:W/b	ole Model	internal ener	gy		ternal work		
HG - Ho	urglass energy	У		ng interface e	nerg		jid Body stopp	ere	
SDE - Sy	stem damping	ene		ernal work			al energy		
JE - Join	nt internal ener	дХ		id Body stopp	er e				
SIE - Slid	ling interface e	energ		l energy					
EW - Ex	ternal work								
RBE - Rig	gid Body stopp	ber e							
TE - Tota	al eneroy								





Improved Fonts

To make it easier to create publication-quality images and simplify the communication of your work:

- The range of font sizes is extended to cope with a wider range of displays.
- Font quality has been improved to include an 'antialias' option by default for better appearance.
- A wider range of fonts are now supported for menus.

These options can be accessed via the Menu Attributes panel.

_	Menu	Attributes	? — [] ;
Dismiss	Save_Settings	HELP New Pane	el
Display Fac	1.20	0.5 (larger) 2.0 (smal	ler)
Font size:	C Tiny Small Default Large Huge	Plain Anti-alias	Explain fonts Permit scaling Cached fonts
Menus font:	Helvetica		•
Listing font:	Courier New		•
CJK font:	MS Gothic 12		•

Menus font:	Helvetica 🕨	Choose font category	1
Listing font:	Courier New	Proportional recommended	
CJK font:	MS Gothic 12	Prop normal options	
		Prop light options	
		Prop heavy options	
		Monospaced recommended	
		Mono normal options	
		Mono light options	
		Mono heavy options	
		Explain this	



Buttons

To make buttons easier and more intuitive to use:

- Clickable buttons are now distinguishable on hover by a slight colour change.
- Radio buttons are now a standard size and shape to be more distinct from tickboxes and more recognisable as radio buttons.
- Button spacing has been adjusted for toggle button groups, so that users understand that they are linked together.







Scroll Bars and Sliders

To make navigating lists quicker and easier:

- Scroll bar length is now related to the number of list items visible.
- Left-clicking on an empty area of the scroll bar allows users to jump through sections of the list.
- Right-clicking on an empty area on the scroll bar allows the user to jump to that specific point in the list.
- Slider appearance has been improved to make them more distinct from scroll bars.







T/HIS \rightarrow PRIMER Link





Highlight Output Database Cards in PRIMER

- Most of the entity buttons in the 'Read Data' panel have a dropdown option. If you right-click on an entity button, an 'Edit in PRIMER' option will be displayed.
- 2. This option will open PRIMER (if it is not linked already) and will highlight the database cards required for this specific entity to obtain results from LS-DYNA to be viewed in T/HIS.

	<< Undock	Read	Data	? 🗙
	LS-DYNA	Groups	Keyword	T/HIS Curve
	Bulk Data	Keyboard	CSV	Screen
	ISO	LS-PREPOST	DIAdem	NASTRAN
•	CURVOUT	Equation		
	Global 🔻	Parts 🔻	Part Groups V	Nodes 🔻
ر	Solids 🔻	Beams 🔻	Shells 🔻	Tk Shells 🔻
́ст́р	Stonewalls v	Springs v	Airbags 🔻	Contacts V
	Right click to	edit output in P	RIMER stors	Sliprings
\bigcirc	Reactions v	Joints 🔻	X Sections V	Subsystems v
	Rigid Bodies	Spotwelds v	SPCs 🔻	Boundarys v
	Edit in PRIMER	SPHs 🔻	Tracers V	Pulleys V
	ICFD	CESE	EM	PBLAST V
	Pres Tubes V	Bearings v	CURVOUT V	
	Select Mode	ls New I	Model R	eread Model
	Output c	urve: <mark>% (</mark> highes	:t+1)	
	Key	in :		Apply





Highlight Output Database Cards in PRIMER

- This feature is also available for multiple 3. models. In case of multiple models, after you click on 'Edit in PRIMER', a model selection menu will be mapped which will give you a choice to select the model for which you want database cards to be highlighted.
- You can turn on the required database 4. cards and use them in your next LS-DYNA run to get results related to the specific entities in T/HIS. [See next page]

	<< Undock		Re	ad	Data		2 >	
	LS-DYNA	0	Groups		Keyword		T/HIS Curve	
	Bulk Data	Keyboard			CSV		Screen	
	ISO	LS-PREPOST			DIAdem		NASTRAN	
	CURVOUT	E	quation					
	Global	F	Parts	•	Part Groups		Nodes 🔻	
	Solids 🔹	B	eams	C	Shells	C	Tk Shells *	
	Stonewalls V	S	prings	۲	Airbags	۲	Contacts •	
	Geo Contacta	Se	atbelts	۲	Retractors		Stipringu	
	Reactions •	J	oints	۲	X Sections	۲	Subsystems v	
	Rigid Bodies *	Sp	otwelds	۲	SPCs	۲	Boundarys V	
		5	PHs	•	Tracers	۲	Pulleys •	
		CESE E			EM		PBLAST .	
	Pres Tubes V	es Tubes 🔻 Bearings 🔻 C				•		
	Select Mode	Adels New Model			Model	Reread Model		
	Output c	urve:	% (high	es	t+1)			
	Key	in :	-				Apply	
					- MODE	LA	MENU -C	
Vodel sele will appea multiple	ection m ir in case e model	er e c s	nu of	-	CANCEL Send en M1 M2	tity	HELP	

M





Highlight Output Database Cards in PRIMER

Highlighted database cards will be opened in linked PRIMER.

PRIMER will always highlight the database cards for entities in the same order as they are clicked in T/HIS.

You need to turn on the required cards with relevant values in order to use them in next LS-DYNA run.

IMEK 17.0 - 6	-		EDIT	DATABAS	SE_ <ascii (<="" th=""><th>option> in</th><th>model 1</th><th></th><th></th><th>K ? 🗆 🗙</th><th>-</th><th></th><th>EDIT</th><th>DATABASE</th><th>_<ascii op<="" th=""><th>tion> in r</th><th>model 2</th><th></th><th></th><th>К? 🗆 🗙</th><th></th></ascii></th></ascii>	option> in	model 1			K ? 🗆 🗙	-		EDIT	DATABASE	_ <ascii op<="" th=""><th>tion> in r</th><th>model 2</th><th></th><th></th><th>К? 🗆 🗙</th><th></th></ascii>	tion> in r	model 2			К? 🗆 🗙	
File Keyw	+ Create	5	Reset All	✓ Check	k 🖉 🖉 S	Sketch	8 Only	T.	List		+ Create	5	Reset All	✓ Check	🖉 🖉 Sk	etch	8 Only	v	List		t t
	× Cancel	[]) (.h. X-Refs	A 1	ext Edit					× Cancel	<u>[]</u>		th X-Refs	A Tex	xt Edit					
	testute 1		M				-				Include: M	10 -1	Mantar Flax				-				
	include:	VII <	viaster file.	>							include. Iv	12 <1	viaster mez	2			-				
				DATA	BASE_(AS	SCII) in m	odel 1							DATABA	ASE_(ASC	CII) in mo	del 2				
	Modify selec	ted	3.0E-5	1 🔻	0 🔻	0 🔻			PREF	XTF	Modify select	ted	3.0E-5	1 🔻	0 🔻	0 🔻			PREF) XTF	
	All on/off		DT	BIN	LCUR	IOOPT	OPT1	OPT2	OPT3	OPT4	All on/off		DT	BIN L	CUR IC	DOPT	OPT1	OPT2	OPT3	OPT4	
	ABSTAT			₹	₹	Ŧ					ABSTAT	 ✓ 	2.0E-5	3 🔻	0 🔻	0 🔻					
	ATDOUT			T	T	T					ATDOUT			T	Ŧ	T					
	AVSFLT			T	V	T					AVSFLT			T	T	T					
	BEARING				T						BEARING			Ŧ	Ŧ	Ŧ					
	BNDOUT			T	T						BNDOUT	\checkmark	2.0E-5	3 🔻	0 🔻	0 🔻					
	CURVOUT			T	T	T					CURVOUT	Ш		T	Ŧ	T					
	DCFAIL				V	Ŧ					DCFAIL			Ŧ	Ŧ	Ŧ					
	DEFGEO			T	T	T					DEFGEO			Ŧ	Ŧ	Ŧ					
	DEFORC			T	V						DEFORC	$\mathbf{\mathbf{Z}}$	2.0E-5	3 🔻	0 🔻	0 🔻					
	DESTAT				T						DESTAT			Ŧ	Ŧ	T					
	DISBOUT			T	T	T					DISBOUT			Ŧ	Ŧ	Ŧ					
	ELOUT				V	T					ELOUT	$\mathbf{\mathbf{A}}$	2.0E-5	3 🔻	0 🔻	0 🔻	0	0	0	0	
	GCEOUT			7	T	₹					GCEOUT	\checkmark	2.0E-5	3 🔻	0 🔻	0 🔻					
	GLSTAT	• 🗹	1.0E-4	0 🔻	0 🔻	0 🔻					GLSTAT •	′ 🗹	2.0E-5	3 🔻	0 🔻	0 🔻					
	H3OUT			V	V	T					H3OUT			Ŧ	Ŧ	Ŧ					
	JNTFORC			7		Ŧ					JNIFORC	1	2.0E-5	3 V	0 🔻	0 🔻					
	MATSUM			T	T	Ŧ					MAISUM	\mathbf{r}	2.0E-5	3▼	0 •	0 •					
	MOVIE			T	V	Ŧ					MOVIE	H		T							
	MPGS			T	V	Ŧ					MPGS										
	NCFORC	•		Ŧ	V	Ψ					NCFORC		0.05.5								
	NODFOR			T	V	Ψ					NODFOR	\mathbf{r}	2.0E-5	3 V	0 •	0 •					
	NODOUT			T	₹	T					NODOUT	\mathbf{r}	2.0E-5	3▼	0 •	0 •	0.0	0			
	PBSTAT			T	T	T					PESTAT	\vdash		T		4					
	PLLYOUT			V	V	V					PLLYOUT	\vdash				4					
	PRIUBE			T	V	Ŧ					PRIUBE	H	0.05.5	7	· ·	*					
	REDOUT			T	V	T					REDUUT	Ľ	2.0E-5	¥ ک ک	0 -	0 7					
	RCFORC			V	V	V					RCFORC		2.0E-5	3 -	0 -	0 7					
	RWFORC			T	V	Ŧ					RWFORC	Ľ	2.0E-5	3 7	0 -	0 7					
	SBIOUL			T	V.						561001	Ľ	2.0E-5	3 ▼ 2 ▼	0 -	0 -					Y
	SECFORC				₹						SECFORC		2.0E-5	3 -	0 -	0 -					
	SLEUUI			V	V	V					SPECODE	×.	2.00-5	3 T	0 -	0 7					
	SPUFURC			T		Ŧ					SPUFURC	ľ	2.0E-5	3 *		U V		_			<u> </u>
	SPHOUI			V I	V	The second secon					SPHOUI		2050	7	· ·	~					
	SSSIAL	•									SUFORC		2.0E-5	3 -	0 -	0 7					
	TODINT					-					TODINT	Ě	Z.U⊑-5	3 *		U V					
	TDUIST					-					TDHIST	H									
ting SSSTAT	TRHIST			*	*	v					INTIO			*	*	Ŧ					CN
nsion tests de																					



T/HIS \rightarrow PRIMER Link

T/HIS can automatically locate an associated LS-DYNA keyword file to load in a linked PRIMER session. The logic used to locate the keyword deck has been improved in Oasys Suite 17.0:

1. The model name is now written to the .ztf file and is read by T/HIS. If this model exists, it is auto-loaded in PRIMER. If the .ztf file is missing, the approach depends on filename convention:

If you use the LSTC results filename convention (d3thdt, xtfile)

2. T/HIS looks to see if there is a single LS-DYNA keyword file (.key/.k/.kby or a .gz/.zip variant thereof) in the working directory and auto-loads it in PRIMER.

If you use the Oasys results filename convention (.thf, .xtf)

- 2. T/HIS looks to see if a *<job>*.thf has been loaded. If yes, T/HIS looks for a matching *<job>*.key/.k/.kby or a .gz/.zip variant thereof.
- 3. If a *<job>*.thf is not found, T/HIS tries a similar logic with a potential *<job>*.xtf file.
- 4. Failing all of that, T/HIS looks to see if there is a single LS-DYNA keyword file in the working directory.

The final fall-back, as always, is for you to manually select an input deck to load in PRIMER.



Equations





Equations

There is a new "Equation" option in the Read panel, which allows you to input an equation of the form y = f(x) and plot the corresponding curve. Here, the function f can depend on any of X, t, T, time or TIME, in place of x.

Additionally, curves can be referenced in these equations, using variables of the form c1, C1 or #1 to refer to curve #1. For example the equation y = #1 + #2 is valid and sums curves #1 and #2, allowing multiple individual curve operations to be replaced by a single equation.

Equations can also be used to evaluate *DEFINE_CURVE_FUNCTION sent from PRIMER. See the PRIMER manual and new features presentation for more information.

<< Undock	Rea	d Data	? >			
LS-DYNA	Groups	Keyword	T/HIS Curve			
Bulk Data	Keyboard	CSV	Screen			
ISO	LS-PREPOS	T DIAdem	NASTRAN			
CURVOUT	Equation					
Equation :	y = #1 + #2	*exp(-0.5*x)*sin(4*PI*x)			
O User-define	d X values					
X Axis s	0.00000					
X Axis e	nd :	2.000000				
X axis interval : 0.010000						
🔿 Take X valu	es from curve	# 1				
O Calculate X	values from o	urve variables				
Output Curve :	% (high	est+1)				
Curve Label :	y = #1	= #1 + #2*exp(-0.5*x)*sin(4*PI*x)				
Vse equation	on as curve la	bel				
X Label :						
Y Label :						
Apply						



Equations

- There are several options for specifying the x-values used to plot the equation. The values can be specified explicitly, taken from another curve or calculated from the curves referenced in the equation.
- By default, the curve will use the equation as the label.
- Once an equation curve has been created, the equation can be edited by right-clicking the curve and selecting "Edit equation...", which will automatically overwrite the original curve.
- Equations can also be used in FAST-TCF via the "equation" command and in JavaScript via **Read.Equation**. Details of how to use these options can be found in the user manual.

<< Undock	Read	d Data	? X				
LS-DYNA	Groups	Keyword	T/HIS Curve				
Bulk Data	Keyboard	CSV	Screen				
ISO	LS-PREPOST	DIAdem	NASTRAN				
CURVOUT	Equation						
Equation :	y = #1 + #2*	exp(-0.5*x)*sin(4*PI*x)				
O User-define	d X values						
X Axis s	tart: 0	.000000					
X Axis e	nd : 2	2.000000					
X axis interval : 0.010000							
🔿 Take X valu	es from curve	# 1					
Calculate X	values from cu	urve variables					
Output Curve :	% (highe	est+1)					
Curve Label :	y = #1 +	1 + #2*exp(-0.5*x)*sin(4*PI*x)					
Vse equati	on as curve lab	el					
X Label :							
Y Label :							
Apply							



Add REPORTER to your Workflow

In version 17.0, REPORTER has been fully integrated with D3PLOT and T/HIS. Now, you can seamlessly add plots and graphs to reports as part of your normal post-processing workflow. Automated LS-DYNA reporting is just a few clicks away.





REPORTER can now be launched from D3PLOT and T/HIS





- You have been post-processing an analysis and want to put an image into a report.
- Press the "REPORTER" button above the TOOLS menu to launch REPORTER in a linked, shared memory mode.





Choose a Template to start creating your Report



 Open a new blank template, an existing template or choose from a range of standard layouts to start creating a report.





Ensure Image looks right at Target Aspect Ratio



- Press "Resize" button at the top of the D3PLOT window to resize to the REPORTER item aspect ratio.
- Select item in REPORTER that you want to capture into.





Capture an Image



- Press the **Capture** button at the top of the D3PLOT window to send the capture to REPORTER.
- Capture information populates item in REPORTER.





Reload items from existing REPORTER Templates



• Select item in REPORTER that you want

to reload.



<u>Oas</u>ys



Items can be reloaded into a live POST session



• Selected REPORTER item is reloaded into

the selected window in POST.

Oasys

T/HIS



Generate Templates from REPORTER

- Generate your template by selecting: $File \rightarrow Generate$
- Generation takes place in existing linked POST sessions, reducing the time taken to generate reports.
- Use REPORTER variables to generate your template after each LS-DYNA simulation.

lame	Туре	Description	Read only	Format	Precision	Temporary	Value		
URRENT_PAGE	Number	Current page number	Yes	None	2				
DATE	String	Current date	Yes	None	2				
EFAULT_DIR	Directory	Reporter default directory		None	2		C:/path/to/my/ana	alysis/001	
EFAULT_JOB	File(basename)	Reporter default jobname		None	2		my_lsdyna_simula	tion	
EPORTER_HOME	Directory	Reporter home directory	Yes	None	2		C:\Oasys 17		
EPORTER_TEMP	Directory	Reporter temp directory	Yes	None	2		C:\Users\alasdair.	parkes\Local Set	ttings\Temp\orr
EMPLATE_DIR	Directory	Template directory	Yes	None	2		C:\Oasys 17\repor	ter_library\temp	lates
ME	String	Current time	Yes	None	2				
DTAL_PAGES	Number	Total number of pages	Yes	None	2				
JSER_HOME	Directory	User home directory	Yes	None	2		C:\Users\alasdair.	parkes	
							New	Edit	Delete
] When generatin	g save variables t	to directory: %DEFAULT_D	IR%						Choose





Useful to know...

- PRIMER item capture and generation are unchanged from earlier versions.
- REPORTER has a new Placeholder item type that can be filled with any of D3PLOT, T/HIS or PRIMER items.
- REPORTER can link to both D3PLOT and T/HIS in the same session.
- Captures are now single window / graph to capture a multi-window layout, capture each window into individual REPORTER items and then design your page layout with greater flexibility in REPORTER.
- Variables are now easier to work with and accessible though the REPORTER panel in D3PLOT and T/HIS.
- Existing templates are fully supported and can be edited and generated using the 16.0 method with a simple option in REPORTER.







Similar to the behaviour of locking in D3PLOT and PRIMER, locking one or more curves on a particular graph will stop those curves from becoming visible, until they are unlocked. This is particularly useful in a session with a large number of curves, when you want to only leave a select few curves unlocked in each graph, preventing accidentally unblanking all curves.

Freezing is the equivalent of locking but for visible curves. Freezing a curve on a graph will stop it from being blanked until it is unfrozen.

The remaining unlocked/unfrozen curves can be manipulated, including the use of shortcut keys 'u', 'r' and 'b', without unblanking the locked curves or blanking the frozen curves.





Locking can be applied using the "Lock" button at the top of each graphics box. This will lock all blanked curves on the corresponding graph.

Freezing can be applied by right-clicking a curve in the curve manager, which freezes it on all active graphs, right-clicking one or more curves in the graphics window or using quick pick.









The graph buttons in the curve table can be repurposed by rightclicking the "Graph buttons" tab and selecting "Locking/Freezing" mode or selecting the "Locking/Freezing" button. Clicking on one of the tickboxes will then lock a curve if it is blanked, colouring the box red, or freeze a curve if it is visible, colouring the box green. Clicking any of the buttons along the top row will lock all blanked curves on the corresponding graph.

In this example, 4 curves are visible on each of graphs 1, 2 and 3, all other curves are locked on each graph and the first of the visiable curves on each graph is frozen.







User-defined Colours





User-defined Colours

User-defined colours are available in T/HIS via a new colour popup.

The user-defined colours are created from the colour popup using a colour palette:







There have been a number of improvements made to user-defined colours in T/HIS.

- User-defined colours are created from the colour popup using a colour palette.
- The maximum number of user-defined colours has increased from 6 to 150.
- Colours can be named and these names can be referred to in FAST-TCF scripts.
- Once saved, the same user-defined colours are available in D3PLOT.
- The colours are saved to an XML file, *user_colours.xml*. A *user_colours.xml* file can exist both in the install directory and a user's home area (if any colours are defined in both places, the user's colours take priority), or a location specified by a preference.
- The *user_colours.xml* files will be read by both D3PLOT and T/HIS.
- In JavaScript, the function **Colour.RGB(r, g, b)** can now colour anything in T/HIS. The HEX code for this RGB value will be written directly into any generated FAST-TCF scripts, and thus reproduce the colour exactly.





Datums





Datums







Datums







Additionally:

- FAST-TCF variables can now be used inside datum definitions in FAST-TCF scripts.
- All of the new features have been added to the JavaScript API as well as datum definitions in FAST-TCF and *.dtm* files. Please see the manual for details.





New Preferences





The following preferences have been added to T/HIS:

Preference	Description
this*show_checkpoint_files	 To show/hide checkpoint playback panel upon T/HIS start up The value of the preference can be TRUE/FALSE (default – FALSE)





New Command Line Options





New Command Line Options

The following command line options have been added to T/HIS:

-show_checkpoint_files=<TRUE/FALSE>

- To show/hide checkpoint playback panel upon T/HIS start up.
- The value of the preference can be TRUE/FALSE (default FALSE).

-checkpoint_dir=<directory>

- Directory path to write checkpoint files.
- *<directory>* must be a valid directory name on your system.
- If the value is <**none**> then the checkpoint files are not recorded for the T/HIS session.





FAST-TCF





The following new options for writing FAST-TCF scripts have been added:

Option	Description	Default
Write DIAdem channel names	DIAdem channel names will be written into the FAST-TCF instead of channel numbers. Can be set using preference <i>ftcf_write_diadem_channel_names</i> .	ON
Write colour names	Names of user-defined colours will be written into the FAST-TCF instead of HEX codes. The colour definitions will be added to the comments in the script in case they are missing when replaying the script. Can be set using preference <i>ftcf_write_user_colours</i> .	OFF
Only reference models required by the script	When writing a FAST-TCF script, only models that are required for the curves captured by the script will be referenced, rather than all the models in the session. For example, say there are two models, M1 and M2 in a session, with a single graph that contains data only from model M2. When a FAST-TCF script is written, if this option is on then M2 will be referred to as model 1 in the script, so it can be played back in a session with 1 model. If this option is off, then it will be referred to as model 2, so it can be replayed in the same session with the same result. Can be set using preference <i>ftcf_write_required_models</i> .	ON





The following commands have been added to FAST-TCF:

Command	Arguments	Description
read_diadem	"filename" "channel name"	DIAdem channels can now be read by providing the channel name, enclosed in quotes, in place of the channel number.





JavaScript





New JavaScript Functions – Global Class

The following functions have been added to the T/HIS JavaScript API.

Function	Description	
Graph: g.active	Return 1 if graph g is active, 0 otherwise.	
Group.DeleteGroup(<i>group, auto</i>)	Delete one or all curve groups. The argument <i>group</i> can be either the name or ID of a group, or 0 to delete all groups. Automatically generated groups can only be deleted if the optional argument <i>auto</i> is set to 1.	
Read.Equation(<i>expression</i> , <i>x_val_opt</i> , <i>x_start</i> , <i>x_end</i> , <i>x_interval</i>)	Expression string to define the equation "y = expression", optional arguments to define the x-values used for the curve. For more details see Equations.	





- JavaScript API enhancements:
 - A new slider widget is available for graphical user interfaces.
 - The *onClick* event can now be used for label widgets.





Extending Classes

There have been a few instances where users have extended an existing class in T/HIS by adding their own property (for example adding a 'type' property to the Widget class). When we add new functionality to the API this potentially causes a conflict.

For Arup to be able to extend and enhance the API in the future any constant, property or method names beginning with a lowercase or uppercase letter are reserved.

If you need to add your own properties or methods to one of the existing classes then to avoid any potential future conflict you should ensure that the name begins with either an underscore (_) or a dollar sign (\$) or the name is prefixed with your own unique identifier.

For example if company 'ABC' need to add a property called 'example' then to avoid any potential future conflict use one of:

_example

\$example

ABC_example





Replay of Drag-Drop Files





Replay of Drag-Drop Files

• The checkpoint files will now support replay of the drag and drop of the files into T/HIS graphics area.





Contact Information

ARUP

www.arup.com/dyna

For more information please contact us:

UK	China	India	USA West
The Arup Campus	Arup China	Arup India Pvt Ltd	Oasys Ltd
Blythe Valley Park	39/F-41/F Huaihai Plaza	10th floor, Western Dallas Center	c/o 560 Mission Street Suite 700
Solihull	1045 Huaihai Road (M)	Plot no. 83/1, Knowledge City	San Francisco
B90 8AE	Xuhui District, Shanghai	Rai Durg, Hyderabad-500032	CA 94105
United Kingdom	200031	Telangana, India	United States
	China		
T: +44 121 213 3399	T: +86 21 3118 8875	T: +91 40 69019797 / 98	T: +1 415 940 0959
dyna.support@arup.com	china.support@arup.com	india.support@arup.com	us.support@arup.com

or your local Oasys distributor

Oasys T/HIS

Oasys